


# Yottacontrol A5x Series Distributed Control

## A-5X


### 1. A5x USB DRIVER install (Windows XP 32-bit)




# Yottacontrol A5x Series Distributed Control

## A-5X

### 1. A5x USB DRIVER install (Windows XP 32-bit)



### 2. A5x USB DRIVER install (Windows 7 64-bit)






# Yottacontrol A5x Series Distributed Control

## A-5X

### 2. A5x USB DRIVER install (Windows 7 64-bit)



## A-5X

# Yottacontrol A5x Series Distributed Control

## A-5X

### 3. A5x USB DRIVER install (Windows 8.1 64-bit)

在此通知在Windows 8.1 x64 版本的作業系統下安裝 驅動程式時，發生驅動程式安裝失敗時，請用以下步驟排除

解決方式：(暫時停用 Windows 8.1 驅動程式強制簽章機能)


1. 右下角(變更電腦設定)

2. 點選"更新與復原"




3. 點選【復原】→【進階啟動】→【立即重新啟動】

4. 點選"更新與復原"




5. 點選【進階選項】

6. 點選【啟動設定】



7. 點選【重新啟動】

8. 重新開機後，在啟動畫面點選【7. 停用驅動式強制簽章】



9. 進入系統後，請直接執行驅動程式安裝軟體即可正常安裝

10. 另外在 Windows 8 x64 版本 請參考以下步驟：

a. 請到Setting(變更電腦設定) / 一般 / 進階啟動(非傳統的 Control panel 畫面)

b. 按下 "立即重新啟動" 的按鈕

c. 於接下來出現的藍色畫面下點選 "疑難排解" -> "進階選項" -> "啟動設定" -> "重新開機" 的按鈕。

d. 重新開機後的開機藍色畫面下按數字鍵 "7" 即可選用 "停用驅動程式強制簽章" 的方式來開機。

e. 進入系統後，請直接執行驅動程式安裝軟體即可正常安裝