


Digital Image Folder/Path Setup

At the Setup Menu, Press the "D" key.

Setting the Path for Importing/Exporting Digital Images:

Use this set-up screen to list the drive and folder of your Digital Camera SD Card or Compact Flash Card and 2 other drives/folders that you want to import from. When importing images into the Repair Order, you will be prompted to select the drive and folder you have entered into this screen. This program will not import directly from a digital camera, but instead, it will import from the camera SD Card or CompactFlash from any USB Port.

Press the "I" Key to enter up to 3 different drives and folders to import digital images from.



Press the "E" Key to enter up to 3 different drives and folders to export digital images to. For example, a folder used to store digital images and / or store email photo attachments.

Digital Image Folder/Path Setup

