

Grape 10 version 0.63

Release date: 08 June 2026

Bug fixes

In earlier versions, the printer tools worked only at 720 dpi. This bug was fixed.

The app crashed when the first (chosen) sequence image was missing a serial number and when the sequence contained only one image. Now the app issues an error message and ignores the import action.

Improvements

Resize tool

The vertical DPI setting is now set by default to match that of the sequence images.

In the PAR options, the default is changed to “Free.”

Interlace tool

The vertical DPI default setting is set to match the vertical DPI of the images in the sequence.

Printer testing

In earlier versions, the print resolution pattern width was set to 180 mm and could not be changed. In this version, you can set the width of this pattern to any value.

UI

Now the Return and Escape keys can be used to submit/save and cancel, respectively, in the settings and the patterns windows.

General

In previous versions, all images in TIFF format were saved uncompressed. Now all images in this format are saved with LZW compression. In the current version, the TIFF compression method cannot be changed.

Demo files

Arranged all the demo files of the printer testing in a separate folder. This folder has two sub-folders:

1. One for the 40 lpi example
2. Other for the 40.1 lpi example

Each subfolder contains all files that are used in the book as examples.

License

Reformulated.